Enabling a Network Adapter

First view the available network adapters,

dladm show-dev				
e1000g0	link: up	speed: 100	Mbps	duplex: full
e1000g1	link: up	speed: 100	Mbps	duplex: full
e1000g2	link: unknown	speed: 0	Mbps	duplex: half
e1000g3	link: unknown	speed: 0	Mbps	duplex: half

Often there are issues with network negotiations. I have yet to meet an experienced admin who does not force the modes.

```
cd /kernel/drv
vi e1000g.conf # this will change depending on the adapter
```

Here is an example file with modification,

```
# Driver.conf file for Intel e1000g Gigabit Ethernet Adapter
#
# Copyright (c) 2002, by Intel, Inc.
# All Rights Reserved.
#
#ident "@(#)e1000g.conf 1.1 98/09/22 Intel"
#
# Copyright 2006 Sun Microsystems, Inc. All rights reserved.
# Use is subject to license terms.
#
# ident "@(#)e1000g.conf
                              1.4
                                      06/03/06 SMI"
#
ForceSpeedDuplex=4,4,4,4,4,4,4,4,4,4,4,4,4,4,4,4,4,4;
# This will force Speed and Duplex for following settings for a
typical instance.
       # 1 will set the 10 Mbps speed and Half Duplex mode.
       # 2 will set the 10 Mbps speed and Full Duplex mode.
       # 3 will set the 100 Mbps speed and half Duplex mode.
       # 4 will set the 100 Mbps speed and Full Duplex mode.
       # 7 will let adapter autonegotiate.
AutoNegAdvertised=0,0,0,0,0,0,0,0,0,0,0,0,0,0,0,0,0;
       # This parameter determines the speed/duplex options that will be
       # advertised during auto-negotiation. This is a bitmap with the
       # following settings.
               7 6
                               5
                                            3
       # Bit
                                      4
                                                 2
                                                           1
                                                                 0
       # Setting | N/A | N/A | 1000F | N/A | 100F | 100H | 10F | 10H
       #
       # For example:
       # To advertise 10 Half only AutoNegAdvertised
                                                        1
       # To advertise 10 Full only AutoNegAdvertised
                                                    =
                                                        2
       # To advertise 10 Half/Full AutoNeqAdvertised
                                                        3
                                                     =
       # To advertise 100 Half only AutoNegAdvertised = 4
```

```
# To advertise 100 Full only AutoNegAdvertised = 8
       # To advertise 100 Half/Full AutoNegAdvertised = 12
       # To advertise 1000 Full only AutoNegAdvertised = 32
       # To advertise all speeds AutoNegAdvertised
                                                   = 47
MaxFrameSize=0,0,0,0,0,0,0,0,0,0,0,0,0,0,0,0;
       # 0 is for normal ethernet frames.
       # 1 is for upto 4k size frames.
       # 2 is for upto 8k size frames.
       # 3 is for upto 16k size frames.
       # These are maximum frame limits, not the actual ethernet frame
       # size. Your actual ethernet frame size would be determined by
       # protocol stack configuration (please refer to ndd command man
pages)
       # For Jumbo Frame Support (9k ethernet packet)
       # use 3 (upto 16k size frames)
# 0: Flow control is completely disabled
       # 1: Rx flow control is enabled (we can receive pause frames
       #
             but not send pause frames).
       # 2: Tx flow control is enabled (we can send pause frames
       #
             but we do not receiving pause frames).
       # 3: Both Rx and TX flow control (symmetric) is enabled.
       # 4: No software override. The flow control configuration
             in the EEPROM is used.
       #
# 1 turns it on and 0 turns it off.
       # Some switches as Cisco 6500/Foundary still operate in TBI mode.
       # This setting will fix the problems seen with odd byte packets.
       # This setting is valid only for 82543GC based copper adapters.
SetMasterSlave=0,0,0,0,0,0,0,0,0,0,0,0,0,0,0,0;
       # 0 sets to hardware default
       # 1 forces master
       # 2 forces slave
       # 3 forces auto
       # This setting controls the PHY master/slave setting. Manually
```

forcing

master or slave can help reduce time to link with some switches
(Planex 08TX and IO Data switches). It is recommended that this
setting remain at the hardware default.

Enable the Adapter

See the state of current and available adapters,

dladm show-dev				
e1000g0	link: up	speed: 100	Mbps	duplex: full
e1000g1	link: unknown	speed: 0	Mbps	duplex: half
e1000g2	link: unknown	speed: 0	Mbps	duplex: half
e1000g3	link: unknown	speed: 0	Mbps	duplex: half

Enable the adapter,

ifconfig e1000g1 plum

5 5 1

Notice the adapter is enabled and at full duplex,

dladm show-dev				
e1000g0	link: up	speed: 100	Mbps	duplex: full
e1000g1	link: up	speed: 100	Mbps	duplex: full
e1000g2	link: unknown	speed: 0	Mbps	duplex: half
e1000g3	link: unknown	speed: 0	Mbps	duplex: half